Asure ID version v5.7.3

Release Notes

August 2008 **Asure ID v5.7.3**

This document provides recent information about Asure ID software including new features, enhancements and upgrade path for v5.7.3

Release Highlights

Asure ID v5.7.3

Contents

Technical Support 2
Asure ID Software Support 2
Upgrade Paths 3
Upgrade Paths to Asure ID v5.7.3 3
Asure ID Application Changes 4
Asure ID v5.7.3 4
Asure ID Application Database Changes 5
Data Model Modifications 5
Function Modifications 6
Stored Procedure Modifications 6
Trigger Modifications 7

© 2007 All Rights Reserved.

Technical Support

Asure ID Software Support

For assistance with any of this subject matter contact the Asure ID Support Services Department.

HID Global Technical Support

Phone: (952) 941-0050
Web: www.fargosupport.com/contact.asp

HID Corporate Information

Address: HID Global 6533 Flying Cloud Drive, Eden Prairie MN 55344
Phone: (952) 941-9470

Upgrade Paths

Upgrade Paths to Asure ID v5.7.3

Use the following grid to determine the upgrade path for Asure ID.

Current Asure ID Version	Upgrade Path
v4.x	No direct upgrade path.
v5.5 or v5.6	Install v5.7.3 over the existing software revision.
v5.7.1 or v5.7.2	Uninstall existing software revision and then install v5.7.3. (**Note**: Please review the steps listed below for saving your existing Templates and Records.)

Version information can be found by selecting **Help** then **About** within the Asure ID software.

- If using Asure ID 5.v7.1 or v5.7.2 any Templates that need to be saved must be exported by selected the **Template** and then the **Export Card Template...** menu option from within the **Card Design Center**.

- Any Records which need to be saved must be to be Exported by selecting the **Database** and then **Export Wizard** menu option from within the **Data Entry Center**. Follow the prompts within the wizard saving any associated Photos as well.

- Remove the existing software by removing it from the **Add or Remove Programs** located within the **Control Panel**. Once the software has been removed restart the computer.

- To launch the Asure ID v5.7.3 installer, double click on the file. Follow the prompts and install the new software. Once the software has been installed restart the computer.

- To re-install the Templates select the **Template** and then **Import Card Templates...** menu option from within the **Card Design Center**. Browse to the file and install.

- To re-install Records select the **Database** and then **Import Wizard…** menu option from within the **Data Entry Center**. Follow the prompts within the wizard to import records as well as associated Photos. All steps surrounding the this procedure are now completed.

Asure ID Application Changes

Asure ID v5.7.3

New Features and Enhancements

Feature	Description	Purpose	Release #
SASI Export	Currently this feature leaves padded zeros on the exported record. This is an incorrect format, as the zeros need to be removed.	This is a standard format used by the education system. This change complies with the correct format required.	v5.7.3
Performance Issues	With the current v5.7.1 and v5.7.2 release, users are unable to make changes to Asure ID while printing. In addition, many performance issues have been seen.	This removes both problems	v5.7.3
Import Wizard – Primary Key	1. Users can decide which field is the primary key using CDC > View> Show all data entries. By default, it's RecordID. They can choose any text or numeric field they want, we won't stop them. 2. When they import - if the data being imported (key field only) exceeds the length of the key field defined in the Asure ID data source, we will "fail" the import. 3. If the key field does not exceed the length of the primary key defined in the Asure ID data source, but other fields in the record do. The import feature will work but will truncate the data for any other fields where the length exceeds the defined length of the Asure ID data souce. 4. There is a 19 character limitation to the size of any field chosen as the primary key.	This allows users more latitude when importing data. By default, the record ID field is the primary key. But many users may have an employee number or social security number and want to use this as a primary.	v5.7.3

Asure ID Application Database Changes

Data Model Modifications

New Tables

Application	New Tables	Release #
N/A		

Function Modifications

New Functions

Application	New Function	Release #
N/A		

Stored Procedure Modifications

New Stored Procedures

Application	New Stored Procedure	Release #
N/A		

Trigger Modifications

New Triggers

Application	Description	Release #
N/A		

REV A